



2.0 TREND MICRO™ Vulnerability Protection Service Pack 1 Installation Guide

Advanced Vulnerability Shielding for Endpoints



Endpoint Security

Trend Micro Incorporated reserves the right to make changes to this document and to the products described herein without notice. Before installing and using the software, please review the readme files, release notes, and the latest version of the applicable user documentation, which are available from the Trend Micro Web site at:

<http://docs.trendmicro.com/en-us/enterprise/vulnerability-protection.aspx>

Trend Micro, the Trend Micro t-ball logo, and Trend Micro Vulnerability Protection are trademarks or registered trademarks of Trend Micro Incorporated. All other product or company names may be trademarks or registered trademarks of their owners.

Copyright © 2014. Trend Micro Incorporated. All rights reserved.

Document Part No. APEM26818/141204

Release Date: December 2014

Document Version No.: 2.0

Product Name and Version No.: Trend Micro Vulnerability Protection 2.0 SP1

Protected by U.S. Patent Nos.: 7,630,982; 8,220,041; 8,505,092; 8,549,282; 7,930,747; 8,510,791; 7,996,896; 8,171,547; 8,230,508

The user documentation for Trend Micro Vulnerability Protection 2.0 SP1 is intended to introduce the main features of the software and installation instructions for your production environment. You should read through it prior to installing or using the software.

Detailed information about how to use specific features within the software are available in the online help file and the Knowledge Base at Trend Micro website.

Trend Micro is always seeking to improve its documentation. Your feedback is always welcome. Please evaluate this documentation on the following site:

<http://www.trendmicro.com/download/documentation/rating.asp>

Table of Contents

Preface

Preface	v
Trend Micro Vulnerability Protection Documentation	vi
Audience	vi
Document Conventions	vii

Chapter 1: Introduction

About Vulnerability Protection	1-2
Vulnerability Protection Components	1-2
Features	1-2

Chapter 2: Preparing for Installation

Installation Requirements	2-2
Performance Recommendations	2-3
System Requirements	2-4
Multi-Node Manager	2-6
Co-Located Relay-enabled Agent	2-7
Scaling for Large Installations	2-7

Chapter 3: Installation

Installation Tasks	3-2
Installing the Database	3-2
Account Details	3-3
Communication with SQL Server	3-4
Installing Vulnerability Protection Manager	3-4
Installing Vulnerability Protection Manager	3-4

Installing Vulnerability Protection Agent	3-16
Importing Agent Software	3-16
Exporting the Agent Installer	3-17
Installing Vulnerability Protection Agent	3-18
Uninstallation	3-21
Uninstalling Manager Using the Uninstallation Program	3-22
Uninstalling Vulnerability Protection Agent Using the Uninstallation Program	3-22
Uninstalling from the Command Line	3-23

Chapter 4: Upgrading

Upgrading Vulnerability Protection Manager	4-2
Upgrading Agents from Vulnerability Protection Manager	4-5

Chapter 5: Post-Installation Tasks

Verifying a Successful Installation	5-2
Managing Multiple Nodes	5-3
Adding a Manager Node	5-3
Viewing Nodes	5-3
Decommissioning Nodes	5-6
Activating the Vulnerability Protection Agent	5-6
Enabling Relay Functionality	5-7
Configuring a Software Update Server	5-8
Web Server Requirements	5-8
Folder Structure	5-9
Using the New Software Repository	5-10

Appendix A: Ports Used by Trend Micro Vulnerability Protection

Vulnerability Protection Manager Ports	A-2
Vulnerability Protection Agent Ports	A-2

Appendix B: Configuring the Settings.Properties File

Format	B-2
Required Values	B-2
Optional Values	B-2
Appendix C: Installation Output	
Successful Installation	C-2
Unsuccessful Installation	C-3
Appendix D: Trend Micro Vulnerability Protection Memory Usage	
Configuring the Installer's Maximum Memory Usage	D-2
Configuring the Manager's Maximum Memory Usage	D-2
Appendix E: Performance Profiles	
Changing the Performance Profile	E-2
Appendix F: SSL Authentication Certificate	
Creating an SSL Authentication Certificate	F-2
Appendix G: Frequently Asked Questions (FAQs)	
Frequently Asked Questions	G-2
Appendix H: Troubleshooting	
Troubleshooting	H-2
Index	
Index	IN-1

Preface

Preface

Welcome to the Trend Micro™ Vulnerability Protection *Installation Guide*. This document discusses requirements and procedures for installing the Vulnerability Protection Manager and Agents.

Topics in this chapter:

- *Trend Micro Vulnerability Protection Documentation on page vi*
- *Audience on page vi*
- *Document Conventions on page vii*

Trend Micro Vulnerability Protection Documentation

Trend Micro Vulnerability Protection documentation includes the following:

TABLE 1. Vulnerability Protection Documentation

DOCUMENTATION	DESCRIPTION
Installation Guide	A PDF document that discusses requirements and procedures for installing Trend Micro Vulnerability Protection Manager and Agents.
Administrator's Guide	A PDF document that provides information on the main product tasks, usage advice, reference data, and field-specific information such as valid parameter ranges and optimal values.
Help	HTML files compiled in WebHelp or CHM format that provide "how to's", usage advice, and field-specific information. The Help is accessible from Trend Micro Vulnerability Protection Manager and Agents.
Readme file	Contains a list of known issues and basic installation steps. It may also contain late-breaking product information not found in the Help or printed documentation
Knowledge Base	An online database of problem-solving and troubleshooting information. It provides the latest information about known product issues. To access the Knowledge Base, go to the following website: http://esupport.trendmicro.com

Download the latest version of the PDF documents and readme at:

<http://docs.trendmicro.com/en-us/enterprise/vulnerability-protection.aspx>

Audience

Trend Micro Vulnerability Protection documentation is intended for the following users:

- Trend Micro Vulnerability Protection Administrators: Responsible for installing and managing the manager and agents. These users are expected to have advanced networking and server management knowledge.
- End users: Users who have Trend Micro Vulnerability Protection Agent installed on their endpoints. The skill level of these individuals ranges from beginner to power user.

Document Conventions

The documentation uses the following conventions.

TABLE 2. Document Conventions

CONVENTION	DESCRIPTION
UPPER CASE	Acronyms, abbreviations, and names of certain commands and keys on the keyboard
Bold	Menus and menu commands, command buttons, tabs, and options
<i>Italics</i>	References to other documents
Monospace	Sample command lines, program code, web URLs, file names, and program output
Navigation > Path	The navigation path to reach a particular screen For example, File > Save means, click File and then click Save on the interface
 Note	Configuration notes
 Tip	Recommendations or suggestions
 Important	Information regarding required or default configuration settings and product limitations

CONVENTION	DESCRIPTION
 WARNING!	Critical actions and configuration options

Chapter 1

Introduction

This chapter introduces Trend Micro™ Vulnerability Protection and provides an overview of its features and capabilities.

Topics in this chapter:

- *About Vulnerability Protection on page 1-2*
- *Vulnerability Protection Components on page 1-2*
- *Features on page 1-2*

About Vulnerability Protection

Trend Micro Vulnerability Protection provides advanced vulnerability shielding against zero-day threats and blocks exploits before a patch can even be deployed. Trend Micro Vulnerability Protection is a standalone product replacement for Intrusion Defense Firewall (OfficeScan module) and works in conjunction with other complete user protection solutions including Control Manager for central management.

Vulnerability Protection Components

Trend Micro Vulnerability Protection consists of the following components:

TABLE 1-1. Trend Micro Vulnerability Protection Components

COMPONENT	DESCRIPTION
Vulnerability Protection Manager	The centralized web-based management console used by administrators for configuring security policy and deploying protection to the Vulnerability Protection Agent
Vulnerability Protection Agent	The security agent deployed directly on endpoints to provide Intrusion Prevention and Firewall protection

Features

The following table lists the features of Trend Micro Vulnerability Protection.

TABLE 1-2. Trend Micro Vulnerability Protection Features

FEATURES	DESCRIPTION
Firewall	<ul style="list-style-type: none"> • Centralizes management of the server firewall policy • Supports virtual machine zoning and prevents Denial of Service (DoS) attacks <hr/> <p> Note</p> <p>Running both OfficeScan firewall and Trend Micro Vulnerability Protection firewall, regardless of whether Vulnerability Protection firewall is active, may lead to unpredictable behavior on some Windows XP/2003 systems.</p> <p>Trend Micro recommends uninstalling the OfficeScan firewall driver to resolve the issue.</p> <p>For more information, see http://esupport.trendmicro.com/solution/en-us/0122179.aspx.</p>
Intrusion Prevention	<ul style="list-style-type: none"> • Uses vulnerability rules to shield known vulnerabilities from an unlimited number of exploits • Automatically shields newly discovered vulnerabilities within hours through a rapid deployment of rules to thousands of servers without requiring a system restart • Enables compliance with PCI Requirement 6.6 for the protection of web applications and the data that they process • Defends against SQL injection attacks, cross-site scripting attacks, and other web application vulnerabilities • Shields vulnerabilities until code fixes are available • Increases visibility into, or control over, applications accessing the network • Identifies malicious applications accessing the network and reduces the vulnerability exposure of your servers

Chapter 2

Preparing for Installation

This chapter provides the information necessary before installing Trend Micro Vulnerability Protection.

Topics in this chapter:

- *Installation Requirements on page 2-2*
- *Performance Recommendations on page 2-3*
- *System Requirements on page 2-4*
- *Co-Located Relay-enabled Agent on page 2-7*
- *Scaling for Large Installations on page 2-7*

Installation Requirements

The following table lists the requirements for the installation.

TABLE 2-1. Installation Requirements

INSTALLATION INFORMATION	DESCRIPTION
Installation packages	Place the installation package for the Vulnerability Protection Manager and the Vulnerability Protection Agent on the target endpoints.
Administrator privileges	You need to have Administrator privileges on the endpoints on which you will install Trend Micro Vulnerability Protection software components.
License (Activation codes)	<p data-bbox="505 636 1092 740">During installation, the Setup Wizard prompts you to type an Activation Code. You can use the Registration Key that came with the product to obtain an Activation Code online from the Trend Micro website.</p> <hr data-bbox="505 776 1092 779"/> <p data-bbox="505 792 1092 961"> Note If you do not activate your product during registration, you can do so at a later time from the product console. However, Vulnerability Protection provides a limited feature set until the activation process is complete.</p>

INSTALLATION INFORMATION	DESCRIPTION
Network communication	<p>Communication between the manager and its agents uses DNS host names by default. In order for a successful agent deployment, you must ensure that each endpoint can resolve the host name of the manager. This may require the Vulnerability Protection Manager endpoint to have a DNS entry or an entry in the agent endpoint's host file.</p> <hr/> <p> Note The Setup Wizard requires the host name during the Vulnerability Protection Manager installation procedure. If you do not have DNS, type an IP address instead.</p>
Ports	<p>Trend Micro Vulnerability Protection requires several dedicated ports that must remain open.</p> <p>For more information, see Ports Used by Trend Micro Vulnerability Protection on page A-1.</p>
Reliable time stamps	<p>All endpoints on which Trend Micro Vulnerability Protection software is running should be synchronized with a reliable time source such as a Network Time Protocol (NTP) server.</p>

Performance Recommendations

Many Vulnerability Protection Manager operations require high CPU and memory resources. Trend Micro recommends that the Vulnerability Protection Manager endpoint should have four cores and sufficient RAM in high scale environments.

The database should be installed on hardware that is equal to or better than the specifications of the Vulnerability Protection Manager endpoint. For optimal performance, the database should have 8 to 16 GB of RAM and fast access to local or network storage. Trend Micro recommends consulting a database administrator on the best database configuration and the ideal maintenance plan.

System Requirements

The following tables list the system requirements for installing Trend Micro Vulnerability Protection Manager and Agent.

TABLE 2-2. Vulnerability Protection Manager System Requirements

HARDWARE/SOFTWARE	SPECIFICATIONS
Memory	4 GB (8 GB recommended)
Disk space	1.5 GB (5 GB recommended) <hr/>  Note Trend Micro recommends allocating 13 GB of disk space when installing Vulnerability Protection Manager with the embedded Microsoft SQL Server Express database. <hr/>
Operating system	<ul style="list-style-type: none"> • Microsoft™ Windows Server® 2012 R2 (64-bit) • Microsoft™ Windows Server® 2012 (64-bit) • Microsoft™ Windows Server® 2008 R2 with SP1 (64-bit) • Microsoft™ Windows Server® 2008 with SP2 (32-bit and 64-bit) • Microsoft™ Windows Server® 2003 R2 with SP1 or SP2 (32-bit and 64-bit) • Microsoft™ Windows Server® 2003 with SP2 (32-bit and 64-bit)

HARDWARE/SOFTWARE	SPECIFICATIONS
Database	<ul style="list-style-type: none"> • Oracle 11g • Oracle 10g • Microsoft™ SQL Server® 2014 • Microsoft™ SQL Server® 2014 Express • Microsoft™ SQL Server® 2012 (All Service Packs) • Microsoft™ SQL Server® 2012 Express (All Service Packs) • Microsoft™ SQL Server® 2008 (All Service Packs) • Microsoft™ SQL Express 2008 R2 SP2 embedded <hr/> <p> Tip Installing SQL Express 2008 R2 SP2 requires the .NET Framework 2.0 SP2 and Windows installer 4.5. On Windows 2008 and above, Trend Micro recommends using .NET Framework 3.5 SP1.</p>
Web browser	<ul style="list-style-type: none"> • Mozilla® Firefox® 12+ • Microsoft™ Internet Explorer® 11.x • Microsoft™ Internet Explorer® 10.x • Microsoft™ Internet Explorer® 9.x • Google Chrome™ 20+ <hr/> <p> Note Cookies must be enabled on all browsers.</p>

TABLE 2-3. Vulnerability Protection Agent System Requirements

HARDWARE/SOFTWARE	SPECIFICATIONS
Memory	128 MB
Disk space	500 MB

HARDWARE/SOFTWARE	SPECIFICATIONS
Operating system	<ul style="list-style-type: none"> • Microsoft™ Windows® 8.1 (32-bit and 64-bit) • Microsoft™ Windows Server® 2012 R2 (64-bit) • Microsoft™ Windows® 8 (32-bit and 64-bit) • Microsoft™ Windows Server® 2012 (64-bit) • Microsoft™ Windows® 7 with SP1 (32-bit and 64-bit) • Microsoft™ Windows Server® 2008 R2 with SP1 (64-bit) • Microsoft™ Windows Server® 2008 (32-bit and 64-bit) • Microsoft™ Windows® Vista with SP2 (32-bit and 64-bit) • Microsoft™ Windows Server® 2003 with SP1 (32-bit and 64-bit) and patched with "Windows Server 2003 Scalable Networking Pack" • Microsoft™ Windows Server® 2003 with SP2 (32-bit and 64-bit) • Microsoft™ Windows Server® 2003 R2 with SP2 (32-bit and 64-bit) • Microsoft™ Windows® XP with SP2 or SP3 (32-bit) • Microsoft™ Windows® XP with SP2 (64-bit)

Multi-Node Manager

Vulnerability Protection Manager can be run as multiple nodes operating in parallel using a single database. Running the manager as multiple nodes provides increased reliability, redundant availability, virtually unlimited scalability, and better performance.

Each node is capable of all tasks and no node is more important than any of the others. Users can sign into any node to carry out their tasks. When one node becomes unavailable, this does not lead to the loss of any data nor does it prevent the manager from completing any task.

Each node must be running the same version of the manager software. When performing an upgrade of the manager software, the first manager to be upgraded takes over all Vulnerability Protection Manager duties and shuts down all other Vulnerability Protection Manager nodes. The other nodes appear as “Offline (Upgrade Required)” on the **Network Map with Activity Graph** of the **System Activity** panel under **System Information**. After each node is upgraded, the node goes back online and resumes all manager tasks.

For more information, see [Managing Multiple Nodes on page 5-3](#).

Co-Located Relay-enabled Agent

A Vulnerability Protection deployment requires at least one Vulnerability Protection Relay. Relays distribute Software Updates to agents which keep your protection up to date. Trend Micro recommends installing a Relay-enabled agent on the same endpoint as the Vulnerability Protection Manager to protect the host computer and to function as a local Relay.

During the installation of the Vulnerability Protection Manager, the installer will look in its local directory for an agent installation package.

If an agent installation package is unavailable, the installation of the Vulnerability Protection Manager proceeds without the agent. The Relay-enabled agent may be installed at a later time.

For more information, see [Installing Vulnerability Protection Agent on page 3-16](#) and [Activating the Vulnerability Protection Agent on page 5-6](#).

Scaling for Large Installations

To improve the performance of Trend Micro Vulnerability Protection installations with more than 1,000 managed endpoints, Trend Micro recommends the following measures:

- Install the manager on an endpoint with a minimum of a quad-core processor and 8 GB of available memory



Note

Installing Microsoft SQL Server Express on an endpoint with a 32-bit dual-core processor and 4 GB of available memory causes high CPU usage issues. As a result, completing resource-intensive tasks such as recommendation scans can take as long as four days.

- Upgrade the server hardware
-



Note

For example, upgrading to 64-bit dual node 8-core processors increases processing speeds.

- Use an external database
-



Note

For more information on installing a standalone database, see [Installing the Database on page 3-2](#).

Chapter 3

Installation

This chapter describes the installation steps for Trend Micro Vulnerability Protection.

Topics in this chapter:

- *Installation Tasks on page 3-2*
- *Installing the Database on page 3-2*
- *Installing Vulnerability Protection Manager on page 3-4*
- *Installing Vulnerability Protection Agent on page 3-18*

Installation Tasks

The following are the primary installation tasks:

1. Install the database if you intend to use a standalone server.

For more information, see [Installing the Database on page 3-2](#).

2. Install Vulnerability Protection Manager.

For more information, see [Installing Vulnerability Protection Manager on page 3-4](#).

3. Install Vulnerability Protection Agent.

For more information, see [Installing Vulnerability Protection Agent on page 3-18](#).

Installing the Database

If you intend to use a standalone server, you must first install the database software, create a database, and create a user account before installing Vulnerability Protection Manager.



Important

Vulnerability Protection does not support special characters in the database user name.

The following table lists the recommended databases for enterprise deployments.

TABLE 3-1. Databases for Enterprise Deployment

DATABASE	VERSION
Microsoft™ SQL Server	<ul style="list-style-type: none">• 2014• 2012• 2008 R2• 2008

DATABASE	VERSION
Microsoft™ SQL Server Express™	<ul style="list-style-type: none"> • 2014 • 2012 • 2008 R2 SP2
Oracle Database	<ul style="list-style-type: none"> • 11g • 10g



Tip

If you only plan to test or evaluate Trend Micro Vulnerability Protection in a small-scale environment, you may also use the embedded Apache Derby database.

Account Details

The following table lists the recommended configuration settings for the standalone database.

TABLE 3-2. Database Configuration Settings

DATABASE	ROLES	PERMISSIONS
Microsoft SQL Server	<ul style="list-style-type: none"> • DB_Creator Server Roles • DB_Owner (of Vulnerability Protection Manager) 	N/A
Oracle Database	<ul style="list-style-type: none"> • CONNECT • RESOURCE 	<ul style="list-style-type: none"> • CREATE TABLE • CREATE SEQUENCE • CREATE TRIGGER



Note

Take note of the database account details. The Setup Wizard requires the database account details during the Vulnerability Protection Manager installation process.

Communication with SQL Server

When using named pipes to connect to SQL Server, a properly authenticated Microsoft Windows communication channel must be available between the Vulnerability Protection Manager's host and the SQL Server host. If no such communication channel is available, Vulnerability Protection Manager cannot communicate with SQL Server over named pipes.

For more information on using named pipes, see [http://technet.microsoft.com/en-us/library/ms189307\(v=sql.105\).aspx](http://technet.microsoft.com/en-us/library/ms189307(v=sql.105).aspx).

Installing Vulnerability Protection Manager

This section describes how to install Vulnerability Protection Manager.

Installing Vulnerability Protection Manager

Procedure

1. Run any of the following installation packages:


INSTALLER	DESCRIPTION
VP-Windows-2.0.<XXXX>.i386	Standard installer for 32-bit operating systems
VP-Windows-2.0.<XXXX>.x64	Standard installer for 64-bit operating systems
VP-Windows-2.0.<XXXX>.i386-sqlexp	Installer embedded with Microsoft SQL Server Express and Vulnerability Protection Agent installation package for 32-bit operating systems
VP-Windows-2.0.<XXXX>.x64-sqlexp	Installer embedded with Microsoft SQL Server Express and Vulnerability Protection Agent installation package

INSTALLER	DESCRIPTION
	with Relay option for 64-bit operating systems

**Note**


<XXXX> is the installer build number.

The **Trend Micro Vulnerability Protection Manager Setup Wizard** screen appears.



2. Click **Next**.

The **License Agreement** screen appears.



3. Click **I accept the terms of the Trend Micro license agreement** to continue the installation.




Note

If you do not accept the terms, select **I do not accept the terms of the Trend Micro license agreement** and click **Cancel**. This terminates the installation without modifying your operating system.

4. Click **Next**.

The **Installation Path** screen appears.




5. Specify a location for the Vulnerability Protection Manager files.

**Note**

When selecting a folder, the installer appends the suggested folder name at the end of the selected path. To avoid duplication, review the folder path when using the **Browse** button.

6. Click **Next**.

The **Database** screen appears.



Note

The **Embedded Microsoft SQL Server Express** option is only available when using an installer embedded with Microsoft SQL Server Express.

7. Select from the following database options:

TYPE	DESCRIPTION
Embedded Microsoft SQL Server Express	<p>The Vulnerability Protection Manager installs the Microsoft SQL Express 2008 R2 included in the installation package.</p> <hr/> <p> Note This option is only available when using either of the installer packages embedded with Microsoft SQL Server Express.</p>
Microsoft SQL Server	<p>The Vulnerability Protection Manager accesses the previously installed Microsoft SQL Server.</p>


TYPE	DESCRIPTION
	 Important If you select Microsoft SQL Server, you must first create the database before installing Vulnerability Protection Manager. For more information, see Installing the Database on page 3-2 .
Oracle	The Vulnerability Protection Manager accesses the previously installed Oracle database.  Important If you select Oracle, you must first create the database before installing Vulnerability Protection Manager. For more information, see Installing the Database on page 3-2 .
Embedded (Trial and demonstration)	The Vulnerability Protection Manager installs the Apache Derby included in the installation package.

8. Depending on the selected database, provide the following in the **Connection Settings** section:

ITEM	DESCRIPTION
Host name	The label assigned to a single endpoint connected to a network
Database name	The name assigned to a specific database
Transport	Select one of the following: <ul style="list-style-type: none"> • Transmission Control Protocol (TCP) • Named Pipe <hr/>  Note These options are only available for Microsoft SQL Server
User name	The user name for the System Administrator (sa) account
Password	The password for the System Administrator (sa) account

9. Click **Next**.

The **Product Activation** screen appears.



10. Type your Activation Code.




Note

If you select **Continue without activation**, you can activate your product at a later time using the web console by going to **Administration > Licenses**.

11. Click **Next**.

The **Address and Ports** screen appears.



12. Provide the following:

- **Manager address:** A resolvable host name, fully-qualified domain name (FQDN), or IP address




Note

If DNS is not available in your environment, or if some endpoints are unable to use DNS, use a fixed IP address instead of a host name.

- **Manager port:** The HTTPS port responsible for the Vulnerability Protection Manager web console
- **Heartbeat port:** The port on which the manager listens for communication from agents

13. Click **Next**.

The **Administrator Account** screen appears.



The screenshot shows a window titled "Trend Micro Vulnerability Protection Manager 2.0.1494 Setup Wizard" with a sub-header "Administrator Account". The window contains the following elements:

- A prompt: "Type a user name and password."
- A "User name:" field containing "MasterAdmin".
- A "Password:" field with 8 dots.
- A "Confirm password:" field with 8 dots.
- A checkbox labeled "Enforce strong passwords" which is checked.
- A "Note" box containing the text: "Strong passwords are a minimum of 8 characters in length and must include:" followed by a bulleted list:
 - Letters and numbers
 - Upper and lower case characters
 - Non-alphanumeric characters
- Navigation buttons at the bottom right: "< Back", "Next >", and "Cancel".

14. Type the user name and password for the administrator account. Retype the password to confirm.




Tip

Trend Micro recommends selecting **Enforce strong passwords**. Strong passwords are a minimum of 8 characters in length and must include:

- Letters and numbers
- Upper and lower case characters
- Non-alphanumeric characters

15. Click **Next**.

The **Security Update Configuration** screen appears.




16. Accept the **Create Scheduled Task to regularly check for Security Updates** option (enabled by default).

**Tip**

Trend Micro recommends enabling this feature to automatically retrieve the latest components or check for new software. You can configure updates at any time using the web console by going to **Administration > Updates**.

17. If the network requires that Vulnerability Protection uses a proxy server, select **Use Proxy Server when connecting to Trend Micro for Security Updates** and configure the proxy settings.
18. Click **Next**.

The **Co-Located Relay-enabled Agent** screen appears.




Note

This option is only available when installing on endpoints running 64-bit operating systems.

19. Select **Install Relay-enabled Agent**.
20. Click **Next**.


The **Installation Information** screen appears.



21. Verify the information and click **Install** to start installing Vulnerability Protection Manager.

The installation process begins.

22. On the **Installation Complete** screen, click **Finish** to exit the Setup Wizard.



Installing Vulnerability Protection Agent

This section describes how to install Vulnerability Protection Agents.

Importing Agent Software

The Vulnerability Protection Agent installer may be downloaded from the Download Center. However, Trend Micro recommends importing the installation package into Vulnerability Protection Manager first, and then exporting the Vulnerability Protection Agent installation package.

Completing this step ensures that the Agent installer is readily available from the Vulnerability Protection Manager web console.

Procedure

1. Download an agent installation package and save to a local folder.
2. On the Vulnerability Protection Manager web console, go to **Administration > Updates > Software > Local**.

The **Local Software** screen appears.

3. Click **Import**.
4. The **Import Software** screen appears.
5. Click **Choose File** and locate the agent installation package from the local folder.
6. Click **Next**.
7. Click **OK** if a confirmation screen appears.
8. Click **Finish**.

The import progress bar appears.

9. Click **Close**.
-

Exporting the Agent Installer

After importing the Vulnerability Protection Agent into Vulnerability Protection Manager, you need to export and save the installation package to a local folder.

Procedure

1. On the Vulnerability Protection Manager web console, go to **Administration > Updates > Software > Local**.
2. Select the agent.
3. From the menu bar, click **Export > Export Installer**.

The installer is exported into an installer package.

4. Save the agent to a local folder.
-

Installing Vulnerability Protection Agent

Procedure

1. Run any of the following installation packages:


INSTALLER	DESCRIPTION
VPAgent-Windows-2.0.2-<XXXX>.i386	Standard installer for 32-bit operating systems
VPAgent-Windows-2.0.2-<XXXX>.x86_64	Standard installer for 64-bit operating systems



Note


<XXXX> is the installer build number.

The **Welcome** screen appears.



2. Click **Next**.

The **End-User License Agreement** screen appears.




3. Click **I accept the terms of the Trend Micro license agreement** to continue the installation.

**Note**


If you do not accept the terms, click **Cancel**. This terminates the installation without modifying your operating system.

4. Click **Next**.


The **Destination Folder** screen appears.



5. Specify a location for the Vulnerability Protection Agent files and click **Next**.
A confirmation screen appears.



6. Click **Install** to start installing Vulnerability Protection Agent.
The installation process begins.
7. On the **Completed the Trend Micro Vulnerability Protection Agent Setup Wizard** screen, click **Finish** to exit the Setup Wizard.



The Vulnerability Protection Agent installs and runs immediately after the installation completes.

Uninstallation

The following section explains how to uninstall Trend Micro Vulnerability Protection Manager and Agent.

Uninstalling Manager Using the Uninstallation Program

Procedure

1. Uninstall Vulnerability Protection Manager in one of the following ways:
 - From the Start menu:
 - a. On the Vulnerability Protection Manager endpoint, click **Start > Programs > Trend Micro > Trend Micro Vulnerability Protection Manager Uninstaller**.
A confirmation screen appears.
 - b. Click **Yes** to verify the uninstallation.
 - c. Click **Next** to begin uninstalling Vulnerability Protection Manager.
A confirmation screen appears.
 - d. Click **Finish** to close the manager uninstallation program.
 - From Windows Control Panel:
 - a. From the Windows Control Panel, click **Add/Remove Programs**.
 - b. Click **Control Panel > Add or Remove Programs**.
 - c. Locate and double-click "Vulnerability Protection Manager" and follow the on-screen instructions.
-

Uninstalling Vulnerability Protection Agent Using the Uninstallation Program

Procedure

1. From the Windows Control Panel, click **Add/Remove Programs**.
2. Select **Trend Micro Vulnerability Protection Agent** from the list, and click **Change/Remove**.

**Important**

When you uninstall an activated agent from a managed endpoint, Vulnerability Protection Manager does not automatically detect the uninstallation. The endpoint remains listed in the Computers list and its status appears as **Managed (Offline)**. To avoid this, either deactivate the agent from the web console before uninstallation, or delete the endpoint from the Computers list.

Uninstalling from the Command Line

You can uninstall both the Vulnerability Protection Manager and Vulnerability Protection Agent using a command line editor (for example, `cmd.exe`).

To uninstall Vulnerability Protection Manager, use the following commands:

- `Uninstall.exe`
Performs a normal uninstallation
- `Uninstall.exe -q`
Performs a silent uninstallation

To uninstall Vulnerability Protection Agent, use the following commands:

- `msiexec /x <package_name_including_extension>`
Performs a normal uninstallation
- `msiexec /x <package_name_including_extension> /quiet`
Performs a silent uninstallation

Chapter 4

Upgrading

The following are the steps for upgrading a basic Agent-based Vulnerability Protection installation:

1. Upgrade the Vulnerability Protection Manager to version 2.0 SP1.
For more information, see [Upgrading Vulnerability Protection Manager on page 4-2](#).
2. Install at least one Vulnerability Protection Agent with Relay functionality enabled.
For more information, see [Installing Vulnerability Protection Agent on page 3-16](#) and [Enabling Relay Functionality on page 5-7](#).
3. Upgrade the Vulnerability Protection Agents and Relays to version 2.0 SP1.
For more information, see [Upgrading Agents from Vulnerability Protection Manager on page 4-5](#).


Upgrading Vulnerability Protection Manager

This section describes the steps for upgrading to Vulnerability Protection 2.0 SP1.

Procedure


1. Download the Vulnerability Protection Manager 2.0 SP1 installation package from the Trend Micro Download Center (<http://downloadcenter.trendmicro.com/>).
2. Save the installation package to a local folder.
3. Run the installation package.

The **Trend Micro Vulnerability Protection Manager Setup Wizard** screen appears.



4. Click **Next**.

The **License Agreement** screen appears.



5. Click **I accept the terms of the Trend Micro license agreement** to continue the installation.




Note

If you do not accept the terms, select **I do not accept the terms of the Trend Micro license agreement** and click **Cancel**. This terminates the installation without modifying your operating system.


6. Click **Next**.

The **Upgrade Verification** screen appears.



7. Select **Upgrade the existing installation (maintains current configuration)**.
8. Click **Next**.


The **Installation Information** screen appears.



9. Verify the information and click **Install** to start installing Vulnerability Protection Manager.

The installation process begins.

10. On the **Installation Complete** screen, click **Finish** to exit the Setup Wizard.



Upgrading Agents from Vulnerability Protection Manager

This section describes the steps in deploying software upgrades to Agents.



Note

You may also update each agent manually using the steps for installing agents.

For more information, see [Installing Vulnerability Protection Agent on page 3-16](#).

Procedure

1. On the Vulnerability Protection Manager web console, go to **Computers**.
2. Locate the agent that you want to upgrade from the **Computers** list.
3. Right-click the endpoint name and select **Actions > Upgrade Agent Software**.

The **Upgrade Agent Software** screen appears.

4. Select the software version from the **Agent Version** drop-down list.
5. Select an upgrade schedule.
6. Click **OK**.

The agent software is upgraded to the selected version.

Chapter 5

Post-Installation Tasks

This chapter describes the post-installation steps for Trend Micro Vulnerability Protection.

Topics in this chapter:

- *Verifying a Successful Installation on page 5-2*
- *Managing Multiple Nodes on page 5-3*
- *Activating the Vulnerability Protection Agent on page 5-6*
- *Enabling Relay Functionality on page 5-7*
- *Configuring a Software Update Server on page 5-8*

Verifying a Successful Installation

To verify the installation, follow the appropriate steps for your operating system.

Procedure

- For Windows 7 (32- and 64-bit), Windows XP (64-bit), and Windows Server 2003 (32-bit)
 - a. Right-click **Computer** from the Start menu.
 - b. Go to **Manage > Services and Applications > Services**.
 - c. Locate “Vulnerability Protection Manager” or “Vulnerability Protection Agent”.
 - For Windows Server 2008 (32- and 64-bit) and Windows Server 2008 R2 (64-bit)
 - a. Right-click **Computer** from the Start menu.
 - b. Go to **Programs > Administrative Tools > Services**.
 - c. Locate “Vulnerability Protection Manager” or “Vulnerability Protection Agent”.
 - For Windows 8 (32- and 64-bit), Windows 8.1 (32- and 64-bit), Windows Server 2012 (64-bit), Windows Server 2012 R2 (64-bit)
 - a. Click the **Desktop** tile from the **Start** screen.
 - b. From the Desktop, right-click **Start**.
 - c. Go to **Computer Management > Services and Applications > Services**.
 - d. Locate “Vulnerability Protection Manager” or “Vulnerability Protection Agent”.
-

Managing Multiple Nodes

**Note**

You must be using either a Microsoft SQL Server or an Oracle database to run multiple nodes.

Adding a Manager Node

To run the Vulnerability Protection Manager as multiple nodes, you must first add a node to an existing database.

**Important**

At no point should more than one instance of the installer be running at the same time. Doing so can lead to unpredictable results, including corruption of the database.

Procedure

1. Follow Steps 1 to 6 of the Vulnerability Protection Manager installation procedure.

**Note**

For more information, see [Installing Vulnerability Protection Manager on page 3-4](#).

2. Type the account details of the database currently in use.

The new node connects to the database.

Viewing Nodes

The **Network Map with Activity Graph** of the **System Activity** panel under **System Information** displays all Vulnerability Protection Manager nodes along with their status, combined activity, and jobs being processed.

**Note**


The Vulnerability Protection Manager processes many concurrent activities in a distributed pool that is executed by all online manager nodes. All activity not derived from user input is packaged as a job and can thus be run on any manager, except for some local jobs that are executed on each node, such as clearing the cache.

Procedure


1. On the Vulnerability Protection Manager web console, go to **Administration > System Information**.

The **System Information** screen appears.


2. Use the **System Activity** drop-down list to view the following information.
 - **Network Map with Activity Graph:** Displays an overview of the manager nodes in the network and a graphical representation of node activities over the last hour




- **Jobs By Node:** Breaks down the number of jobs carried out by each node over the last hour



- **Jobs By Type:** Displays the job types completed by all the nodes over the last hour



- **Total Jobs By Node and Type:** Displays the total number of jobs and job types for each node over the last hour



Decommissioning Nodes

This section describes how to remove or decommission a manager node.

**Note**

A node must be offline before it can be decommissioned.

Procedure

1. Go to **Administration > System Information > System Activity (Over The Last Hour) > Network Map with Activity Graph**.

The **Network Map with Activity Graph** appears.

2. Click the Manager Node icon of the node you want to decommission.

The **Properties** screen appears.

3. Under **Options**, click **Decommission**.

A confirmation screen appears.

4. Click **OK**.

The decommissioned node is removed from the **Manager Node** screen.

Activating the Vulnerability Protection Agent

Trend Micro Vulnerability Protection automatically installs and activates the agent if you use the all-in-one Vulnerability Protection Manager package.

You may also choose to install the agent separately. For more information, see [Installing Vulnerability Protection Agent on page 3-18](#).

When using the standalone installation package, you must activate the agent after installation.

Procedure

1. On the Vulnerability Protection Manager web console, go to **Computers > New > New Computer**.

The **New Computer Wizard** appears.

2. Type the host name or IP address of the computer where an agent is installed in the **Hostname** field.
3. Select a policy based on the operating system from the **Policy** drop-down list.
4. Leave the default setting for the **Download Software Updates From** field.
5. Click **Next**.

Vulnerability Protection Manager verifies that an agent is installed on the specified computer.

6. Click **Finish**.
-

Enabling Relay Functionality

You need to manually enable the relay functionality of an agent in any of the following scenarios:

- If you did not choose to install the relay-enabled agent during the Vulnerability Protection Manager installation process.
- If you are using a 32-bit server and you need to install the agent separately on a 64-bit endpoint.



Important

If you are running Windows Firewall, you also need to add a Firewall Rule that allows TCP/IP traffic on port 4122 on the Relay.

Procedure

1. On the Vulnerability Protection Manager web console, go to **Computers**.
2. Locate the agent from the **Computers** list and double-click the agent name.
The **Computer Editor** screen appears.
3. On the **Computer Editor** screen, go to **Overview > Actions > Software**.
4. Click **Enable Relay**.

Vulnerability Protection Manager installs the required plug-ins to enable the Relay Module on the agent.

Configuring a Software Update Server

Vulnerability Protection Software Updates are normally hosted and distributed by Relay-enabled agents. To deploy a Vulnerability Protection Agent on an endpoint, you must first import the software package for the platform into Vulnerability Protection Manager.

If you already have web servers deployed throughout your network, you may choose to let those servers perform the task of Software Update distribution instead of deploying Relays for that purpose. To do so, you will have to mirror the software repository of the Vulnerability Protection Relay on your web servers.

The following information describes how to set up your own software repository on a local web server.



Important

This is a required step for all endpoints running 32-bit operating systems.

Web Server Requirements

The following table lists the requirements for the web server.

TABLE 5-1. Web Server Requirements

ITEM	SPECIFICATION
Disk space	8 GB
Ports	<ul style="list-style-type: none"> <li data-bbox="747 345 1176 394">• 4122: Agent-to-Relay communication (TCP) <li data-bbox="747 410 1176 459">• 4123: Internal Relay communication to localhost (TCP)

Folder Structure

You must create a folder on the software web server which will mirror the structure of the software repository folder of a Trend Micro Vulnerability Protection Relay.



Note

The procedures for mirroring folders depend on your IT environment and are beyond the scope of this documentation.

The default location for the software repository folder on a Windows Relay is C:\ProgramData\Trend Micro\Deep Security Agent\relay\www\dsa\.

Below is the folder structure:

```
|-- dsa
| |-- <Platform>.<Architecture>
| |-- <Filename>
| |-- <Filename>
| |-- ...
```

For example:

```
|-- dsa
|   |-- Windows.x86_64
|   |-- Agent-Core-Windows-9.5.1-1532.x86_64.msi
|   |-- Agent-Core-Windows-9.5.1-1534.x86_64.msi
|   |-- Feature-DPI-Windows-9.5.1-1532.x86_64.dsp
|   |-- Feature-DPI-Windows-9.5.1-1534.x86_64.dsp
```

```
| |-- ...  
| |-- Plugin-Filter-Windows-9.5.1-1532.x86_64.dsp  
| |-- Plugin-Filter-Windows-9.5.1-1534.x86_64.dsp  
| |-- ...
```

**Note**

The `dsa` folder on the Trend Micro Vulnerability Protection Relay contains more files and folders than those illustrated in the example above. However, the only folders you need to mirror when hosting a functioning software repository are the ones containing the files associated with the platform and architecture of the agents in use. You may also choose to mirror the entire `dsa` folder.

Using the New Software Repository

Configure Trend Micro Vulnerability Protection to start using the web server as a software update repository.

Procedure

1. On the Vulnerability Protection Manager web console, go to **Administration > System Settings > Updates**.
 2. Under **Software Updates**, type the URL(s) of the folder(s) on your web server(s) containing the mirrored software repository.
 3. Click **Add**.
 4. Click **Save**.
-

Appendix A

Ports Used by Trend Micro Vulnerability Protection

This appendix lists the ports required by Trend Micro Vulnerability Protection Manager and Agent.

Vulnerability Protection Manager Ports

PORT	PURPOSE
25	Communication to a SMTP Server to send email alerts (configurable)
53	For DNS Lookup
389	Connection to an LDAP Server for Active Directory integration (configurable)
636	Connection to an LDAP Server for Active Directory integration (configurable)
1433	Bi-directional Microsoft SQL Server Database port
1434	Bi-directional Microsoft SQL Server Database port
1521	Bi-directional Oracle Database server port
3268	Connection to an LDAP Server for Active Directory integration (configurable)
4119	Used by your browser to connect to the manager
4120	The "heartbeat" port, used by agents to communicate with manager (configurable)

Vulnerability Protection Agent Ports

PORTS	PURPOSE
4118	Manager-to-agent communication
4122	Relay-to-agent communication
4123	Used for internal communication and should not be accessible from outside

Appendix B

Configuring the Settings.Properties File

This section contains information about the contents of the `Settings.Properties` file that you can use during a command line installation of Vulnerability Protection Manager.

Format

Use the following format for each entry in the `Settings.Properties` file:

```
<Screen Name>.<Property Name>=<Property Value>
```

Required Values

The following tables list the required values for the `Settings.Properties` file.

TABLE B-1. “LicenseScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
LicenseScreen.License.1=<value>	<AC for Vulnerability Protection>	LicenseScreen.License.1=XX-XXXX-XXXX-XXXX-XXXX-XXXX-XXXX-XXXX

TABLE B-2. “CredentialsScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
CredentialsScreen.Administrator.Username=<value>	<user name for master administrator>	CredentialsScreen.Administrator.Username=MasterAdmin
CredentialsScreen.Administrator.Password=<value>	<password for the master administrator>	CredentialsScreen.Administrator.Password=12345678

Optional Values

The following tables list the optional values for the `Settings.Properties` file.

TABLE B-3. “UpgradeVerificationScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
UpgradeVerificationScreen. Overwrite=<value>	True False <hr/>  Note The default value is False. Setting this value to True will overwrite any existing data in the database without further prompting.	UpgradeVerificationScreen. Overwrite=False

**Note**

This screen/setting is not referenced unless an existing installation is detected.

TABLE B-4. “DatabaseScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
DatabaseScreen.Database Type=<value>	Embedded Microsoft SQL Server Express Microsoft SQL Server Oracle	DatabaseScreen.Database Type=Microsoft SQL Server Express

PROPERTY	POSSIBLE VALUES	EXAMPLE
DatabaseScreen.Hostname =<value>	<p>The name or IP address of the database host</p> <p>Current host name</p> <hr/>  Note This setting is required for: <ul style="list-style-type: none"> • Oracle • Microsoft SQL Server • Apache Derby 	DatabaseScreen.Hostname =us-administrator
DatabaseScreen.Database Name=<value>	<p>Any string</p> <hr/>  Note This setting is required for: <ul style="list-style-type: none"> • Oracle • Microsoft SQL Server 	DatabaseScreen.Database Name=vpm
DatabaseScreen.Transport =<value>	<p>Named Pipes</p> <p>TCP</p> <hr/>  Note This setting is required for: <ul style="list-style-type: none"> • Microsoft SQL Server 	DatabaseScreen.Transport =TCP

PROPERTY	POSSIBLE VALUES	EXAMPLE
DatabaseScreen.Password= =<value>	<password for database> <hr/>  Note This setting is required for: <ul style="list-style-type: none"> • Oracle • Microsoft SQL Server • Microsoft SQL Server Express 	DatabaseScreen.Password= =12345678
DatabaseScreen.SQLServer.Instance= =<value>	<database instance> <hr/>  Note Leave this value blank to use the default instance. This setting is required for: <ul style="list-style-type: none"> • Microsoft SQL Server 	DatabaseScreen.SQLServer.Instance= MSSQLSERVER
DatabaseScreen.SQLServer.Domain= =<value>	<database domain> <hr/>  Note This setting is required for: <ul style="list-style-type: none"> • Microsoft SQL Server 	DatabaseScreen.SQLServer.Domain= hostname.org

PROPERTY	POSSIBLE VALUES	EXAMPLE
DatabaseScreen.Username= =<value>	<user name for database> <hr/>  Note This setting is required for: <ul style="list-style-type: none">• Oracle• Microsoft SQL Server	DatabaseScreen.Username=sa
DatabaseScreen.SQLServer.UseDefaultCollation=<value>	True False <hr/>  Note The default value is False. This setting is required for: <ul style="list-style-type: none">• Microsoft SQL Server	DatabaseScreen.SQLServer.UseDefaultCollation=False

TABLE B-5. “AddressAndPortsScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
AddressAndPortsScreen.ManagerAddress=<value>	<host name, URL or IP address of the manager host>	AddressAndPortsScreen.ManagerAddress=us-administrator
AddressAndPortsScreen.ManagerPort=<value>	<valid port number> <hr/>  Note The default value is 4119.	AddressAndPortsScreen.ManagerPort=4119

PROPERTY	POSSIBLE VALUES	EXAMPLE
AddressAndPortsScreen.HeartbeatPort=<value>	<valid port number> <hr/>  Note The default value is 4120.	AddressAndPortsScreen.HeartbeatPort=4120

TABLE B-6. “CredentialsScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
CredentialsScreen.UseStrongPasswords=<value>	True False <hr/>  Note True indicates that you want Vulnerability Protection Manager to enforce strong passwords.	CredentialsScreen.UseStrongPasswords=True

TABLE B-7. “SecurityUpdateScreen” Settings

PROPERTY	POSSIBLE VALUES	EXAMPLE
SecurityUpdateScreen.UpdateComponents=<value>	True False <hr/>  Note True indicates that you want Vulnerability Protection Manager to automatically retrieve the latest components.	SecurityUpdateScreen.UpdateComponents=False

Appendix C

Installation Output

The following are sample outputs from successful and unsuccessful command line installations.

Successful Installation

```
Stopping Trend Micro Vulnerability
    Protection Manager Service...
Detecting previous versions of Trend Micro Vulnerability
    Protection Manager...
Upgrade Verification Screen settings accepted...
Database Screen settings accepted...
License Screen settings accepted...
Address And Ports Screen settings accepted...
Credentials Screen settings accepted...
All settings accepted, ready to execute...
Uninstalling previous version
Stopping Services Extracting files...
Setting Up...
Connecting to the Database...
Creating the Database Schema...
Updating the Database Data...
Creating MasterAdmin Account...
Recording Settings...
Creating Temporary Directory...
Installing Reports...
Creating Help System...
Setting Default Password Policy...
Importing Example Security Profiles...
Applying Security Update...
Assigning IPS Filters to Example Security Profiles...
Correcting the Port for the Manager Security Profile...
Correcting the Port List for the Manager...
Creating IP List to Ignore...
Creating Scheduled Tasks...
Creating Asset Importance Entries...
Creating Auditor Role...
Auditing...
Optimizing...
Recording Installation...
Creating Properties File...
Creating Shortcut...
Configuring SSL...
Configuring Service...
Configuring Java Security...
```

```
Configuring Java Logging...
Cleaning Up...
Starting Vulnerability Protection Manager...
Finishing installation...
```

Unsuccessful Installation

This example shows the output generated when the properties file contains an invalid license string.



Note

The [Error] tag in the trace indicates an unsuccessful attempt.

```
Stopping Trend Micro Vulnerability Protection Manager Service...
Detecting previous versions of Trend Micro Vulnerability Protection Manager...
Upgrade Verification Screen settings accepted...
Database Screen settings accepted...
Database Options Screen settings accepted...
[ERROR] The license code you have entered is invalid.
[ERROR] License Screen settings rejected...
Rolling back changes...
```


Appendix D

Trend Micro Vulnerability Protection Memory Usage

This section provides information on how to configure the maximum memory usage for Trend Micro Vulnerability Protection components.

Configuring the Installer's Maximum Memory Usage

The installer uses 1 GB of contiguous memory by default. If the installer is unable to run, you can configure the installer to use less memory.

Procedure

1. Go to the directory where the installer is located.
2. Create a new text file called `VP-Windows-2.0.<xxxx.xxx>.vmoptions` where `<xxxx.xxx>` is the build number of the installer and the platform.

**Note**

For more information on installation package file names, see [Installing Vulnerability Protection Manager on page 3-4](#).

3. Edit the file by adding the line `-Xmx<xxx>` where `<xxx>` is the amount of memory allocated for the installer.

**Note**

`<y>` is the unit of measurement. Use `m` for MB and `g` for GB.

For example, adding the line `-Xmx800m` configures the installer to use 800MB.

4. Save the file and launch the installer.
-

Configuring the Manager's Maximum Memory Usage

The Vulnerability Protection Manager default setting for heap memory usage is 4 GB. For enterprise environments with more managed endpoints, Trend Micro recommends changing the heap memory setting to at least 8 GB.

Procedure

1. Go to the Vulnerability Protection Manager directory.

**Note**

The default directory location is C:\Program Files\Trend Micro
\Vulnerability Protection Manager.

2. Create a new file called `Vulnerability Protection.vmoptions`.
3. Edit the file by adding the line `-Xmx<xxx>y` where `<xxx>` is the amount of memory allocated for the manager.

**Note**

`<y>` is the unit of measurement. Use `m` for MB and `g` for GB.

For example, adding the line `-Xmx10g` configures the manager to use 10 GB.

4. Save the file and restart Vulnerability Protection Manager.
 5. You can verify the new setting by going to **Administration > System Information** and in the **System Details** area, expand **Manager Node > Memory**. The Maximum Memory value should indicate the new configuration setting.
-

Appendix E

Performance Profiles

By default, new installations use the Aggressive Performance Profile which is optimized for a dedicated manager. If Vulnerability Protection Manager is installed on a system with other resource-intensive software it may be preferable to use the Standard Performance Profile.

The Performance Profile also controls the amount of agent-initiated connections that the manager accepts. The default settings for each of the Performance Profiles are designed to keep the number of accepted, delayed, and rejected heartbeats balanced.

Changing the Performance Profile

Procedure

1. On the Vulnerability Protection Manager dashboard, go to to **Administration > System Information**.
 2. Under **System Activity**, click the **Manager Node** button.
The **Properties** screen appears.
 3. Select your preferred **Performance Profile** from the drop-down list.
 4. Click **OK**.
-

Appendix F

SSL Authentication Certificate

The Vulnerability Protection Manager creates a 10-year self-signed certificate for the web browser-to-manager connections. If required, you can replace this certificate with a real certificate.

Once generated, import the certificate into the `.keystore` in the root of the Vulnerability Protection Manager installation directory and have an alias of `tomcat`. The manager uses the certificate in subsequent browser connections.

Creating an SSL Authentication Certificate

Procedure

1. Go to the Vulnerability Protection Manager installation directory located at C:\Program Files\Trend Micro\Vulnerability Protection Manager.
2. Create a new folder called Backupkeystore.
3. Copy `.keystore` and `configuration.properties` to the newly created folder Backupkeystore.
4. Open the command prompt and go to the following location: C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin
5. Run the following command to create a self-signed certificate: C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -genkey -alias tomcat -keyalg RSA -dname cn=vpmserver

**Note**

For more information on generating the certificate, see [Thawte Tomcat Support](#).

6. Type a password.

**Note**

The default name for the certificate is `-dname`. Some Certification Authorities (CAs) require a particular certificate name to sign the Certificate Signing Request (CSR). Consult your CA Admin to confirm your specific requirements.

A new keystore file is automatically created under the user home directory.

To view the `.keystore` file, log on as Administrator and go to C:\Documents and Settings\Administrator.

7. Run the following commands from a command line editor:

- a. To view the newly generated certificate: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -list -v`
- b. To create a CSR file for your CA to sign: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -certreq -keyalg RSA -alias tomcat -file certrequest.csr`

**Note**

Follow the CSR submission guidelines specified by your CA when submitting the CSR file.

- c. To import the CA cert in JAVA trusted keystore: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -import -alias root -trustcacerts -file cacert.crt -keystore "C:/Program Files/Trend Micro/Vulnerability Protection Manager/jre/lib/security/cacerts"`
- d. To import the CA cert in your keystore: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -import -alias root -trustcacerts -file cacert.crt`
- e. To import the certificate response to your keystore: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -import -alias tomcat -file certresponse.txt`

**Note**

A prompt asks if you trust the certificate. Type **Yes**.

- f. To view the certificate chain in you keystore: `C:\Program Files\Trend Micro\Vulnerability Protection Manager\jre\bin>keytool -list -v`
8. Copy the `.keystore` file from your user home directory `C:\Documents and Settings\Administrator` to `C:\Program Files\Trend Micro\Vulnerability Protection Manager\`

9. Open the `configuration.properties` file in folder `C:\Program Files \Trend Micro\Vulnerability Protection Manager`.



Note

It will look something like: `keystoreFile=C:\\\\Program Files\\\\ \\Trend Micro\\\\\\Vulnerability Protection Manager\\trend_manager_program_cap\\\\.keystore port=4119 keystorePass=$1$85ef650a5c40bb0f914993ac1ad855f48216fd0664ed2544bbec6de80160b2fe9800f79f913f28e80381c8e71f2fed96a2aa522ada039a7abfa01542d42dbe3installed=true serviceName= Trend Micro Vulnerability Protection Manager`.

10. Locate the string `keystorePass=<xxxx>` and replace `<xxxx>` with the password you previously supplied.
 11. Save and close the file.
 12. Restart the Vulnerability Protection Manager service.
 13. Connect to the Vulnerability Protection Manager with your browser to see the new SSL certificate signed by your CA.
-

Appendix G

Frequently Asked Questions (FAQs)

This appendix answers various Frequently Asked Questions.

Frequently Asked Questions

QUESTION	ANSWER
Where can I download the installer packages for Trend Micro Vulnerability Protection?	The Trend Micro Download Center: http://downloadcenter.trendmicro.com .
Where can I download the technical documents for Trend Micro Vulnerability Protection?	The Trend Micro Documentation Center: http://docs.trendmicro.com .
Why am I experiencing problems when installing two Vulnerability Protection Managers on the same machine?	Only one instance of the Vulnerability Protection Manager can be installed on any given machine.
What is the default user name and password to log on the Vulnerability Protection Manager console?	<p>You are prompted for a user name and password during installation. The default user name for the manager console is "MasterAdmin". There is no default password. The user name and password are both set during the installation.</p> <hr/> <p> Note The user name is not case-sensitive.</p>
How can I reset the manager console password?	Go to Administration > User Management > Users , right-click on the User and select Set Password....

QUESTION	ANSWER
How can I unlock a locked out user?	<p>On the manager console, go to Administration > User Management > Users, right-click on the User and select Unlock User(s).</p> <p>To unlock a user from the manager, type the following from the Vulnerability Protection Manager's install directory in a command line editor:</p> <pre>vp_c -action unlockout -username <username> [-newpassword NEWPASSWORD]</pre> <p><username> is the user name. Optionally, use <code>-newpassword</code> to set a new password for the user.</p>
How can I use my domain account credentials when logging on to the manager console?	Go to Administration > User Management > Users and select Synchronize with Directory .
How can I mass-deploy the agents to the endpoints?	Organizations typically use existing enterprise software distribution systems such as Microsoft® System Center or Novell® ZENworks® to install agents.
Can I uninstall the Vulnerability Protection Agent from the manager console?	No. You can deactivate the agent from the Vulnerability Protection Manager console, but you must uninstall the agent locally.
How do I deactivate the Vulnerability Protection Agent from the command line?	See "Manually Deactivate/Stop/Start the Agent" in the Administrator's Guide or online help.
How can I manually update the Vulnerability Protection Agent that has no connection with the Vulnerability Protection Manager?	Updating the agent is not possible when disconnected from the manager since the manager must send the security configuration details to the agent.

Appendix H

Troubleshooting

This chapter describes how to troubleshoot issues that may arise with Trend Micro Vulnerability Protection.

Troubleshooting

TABLE H-1. Vulnerability Protection Manager

ISSUE	SOLUTION
<p>Unable to install the Vulnerability Protection Manager</p>	<p>During installation of the Vulnerability Protection Manager, the service may be unable to install properly if the Services screen is open. Close the services screen before installing Vulnerability Protection Manager.</p> <p>If the problem persists, restart the endpoint.</p>
<p>Unable to re-install the Vulnerability Protection Manager on the same endpoint after manually uninstalling Vulnerability Protection Manager and Microsoft SQL Server 2008 R2 Express</p>	<p>This issue occurs because uninstalling Vulnerability Protection Manager and Microsoft SQL Server Express manually does not delete the Vulnerability Protection Manager database.</p> <p>To re-install the manager, users must perform the following steps:</p> <ol style="list-style-type: none"> 1. Click Cancel to end the database installation. 2. Go to the <SQL Server> \MSSQL10_50.TMVUNPROTECT\MSSQL \DATA\ folder. <hr/> <p> Note <SQL Server> is the name of the user-defined Microsoft SQL Server Express database.</p> <hr/> <ol style="list-style-type: none"> 3. Delete vpm.mdf and vpm_log.ldf . 4. Restart the Vulnerability Protection Manager Setup Wizard.

TABLE H-2. Vulnerability Protection Agent

ISSUE	SOLUTION
Vulnerability Protection Agent is unable to start	<p>There are several conditions that can prevent the <code>vp_agent</code> service from starting. The problem may be caused by:</p> <ul style="list-style-type: none"> • Invalid credentials (not valid yet, corrupt, expired, or bad digital signature), • Unable to read the private key (corrupt or hardware was radically changed), or • The listening port already in use. <p>In cases where the Vulnerability Protection Agent is unable to start, it is unable to report to the Vulnerability Protection Manager, so it writes to the Windows Event Log. You should check the Windows Event log to diagnose the problem.</p>
Vulnerability Protection Agent is installed but the user interface displays blank fields	<p>If the manager URL, manager certificate name, and manager certificate fingerprint fields are blank, the agent has not been activated. These fields are blank until the agent has been activated by Vulnerability Protection Manager. Locate the endpoint in the Vulnerability Protection Manager's Computers list, right-click on the endpoint name and select Actions > Activate/Reactivate.</p>

ISSUE	SOLUTION
<p>Getting the following error message in an "Agent Activate Failed" system event: "A client error occurred in the VPM to VPA protocol: HTTP client error received: certificate is not yet valid"</p>	<p>The clock on a Vulnerability Protection Agent machine must be synchronized with the Vulnerability Protection Manager to within 24 hours. If the Vulnerability Protection Agent clock is behind the Vulnerability Protection Manager clock then an agent activation operation will be unsuccessful because the certificate generated for the manager by the Vulnerability Protection Manager is not yet be valid.</p>

Index

A

activation code, 2-2, 3-10

D

database

 account details, 3-3

 installation, 3-2

 named pipes, 3-4

 options, 3-8

documentation, vi, G-2

F

firewall, 1-3

I

installation

 agent, 3-18

 command line, B-1, C-1–C-3

 database, 3-2

 installer package, 2-2, G-2

 manager, 3-4

 performance recommendations, 2-3

 requirements, 2-2

 system requirements, 2-4

 tasks, 3-2

 uninstallation, 3-21

intrusion prevention, 1-3

M

manager console

 administrator account, 3-12, G-2

 password, G-2

memory usage, D-1

 installer, D-2

 manager, D-2

P

performance profiles, E-1

ports, 3-11, A-1

S

SSL authentication certificate, F-1

U

uninstallation, 3-21

 agent, 3-22

 command line, 3-23

 manager, 3-22

updates, 3-13

V

Vulnerability Protection

 about, 1-2

 components, 1-2

 documentation, vi

 features, 1-2



TREND MICRO INCORPORATED

10101 North De Anza Blvd. Cupertino, CA., 95014, USA

Tel:+1(408)257-1500/1-800 228-5651 Fax:+1(408)257-2003 info@trendmicro.com

www.trendmicro.com

Item Code: APEM26818/141204