

SafeSync for Enterprise Quick Installation Card

1 Preparation



System Requirements

- Processor - 64-bit x86 single core (dual-core recommended)
- Memory - 8GB (32GB recommended)
- System disk space - 60GB available for SafeSync installation
- Network card - Two 1GB NIC
- DVD ROM device

Network Requirements

Prepare a static IP address and IP configuration for SafeSync for Enterprise.
Example: 192.168.100.1 (default)

Create a sub-domain for SafeSync. For example: ssfe.YourCompanyDomain.com

Add four DNS records to the DNS server and map the records to the SafeSync IP address. URL examples for DNS records:

- ssfe.YourCompanyDomain.com
- www.ssfe.YourCompanyDomain.com
- soap.ssfe.YourCompanyDomain.com
- dav.ssfe.YourCompanyDomain.com

Active Directory or LDAP accounts: Contact to your AD/LDAP administrator if you are going to import accounts from AD/LDAP. Refer to the AG for further details.

You can also create SafeSync user accounts manually from the SafeSync management console.

2 Installation



Bare-metal Server

- Connect to your assigned network ports switch.
- Insert the installation DVD and boot the server from the DVD.
- Select **Primary Server** as the server to install.
- Specify the IP address configuration settings.
- Wait for installation to complete. This may take up to one hour.

Virtual Machine

VMware ESXi is used in the following procedure as an example.

- Configure the following settings when creating the virtual machine:
 - Configuration: **Typical**
 - Name: Specify a meaningful name
 - Guest OS: Other, Other (64-bit)
 - Network: Create 2 NICs
 - Storage: Specify the where the data is stored (60GB minimum)
 - CPU: Maximum allowable (64-bit x86)
 - RAM: **8GB** or more
- Insert the installation DVD and boot the server from the DVD.
- Select Primary Server as the server to install.
- Specify the IP address configuration settings.
- Wait for installation to complete. This may take up to one hour.

3 Information for IT Administrators



- Web admin: <https://192.168.100.1/administrator/safesync>
- SafeSync command line console: safesync/safesync
- End users: IT admin configures FQDN on the SafeSync for Enterprise web management console.

Example: <https://www.ssfe.YourCompanyDomain.com>

©2013 by Trend Micro Incorporated. All rights reserved. Trend Micro, the t-ball logo are trademarks or registered trademarks of Trend Micro Incorporated. All other company and/or product names may be trademarks or registered trademarks of their owners. Information contained in this document is subject to change without notice.

Item Code: APEQ25955/130508